

# PocketSphinx Plugin

## Administrator Guide

Revision: 5

Distribution: Red Hat / Cent OS

Created: February 3, 2017

Last updated: August 30, 2017

Author: Arsen Chaloyan

# Table of Contents

1	Overview		3
	1.1 1.2 1.3	Applicable Versions	3
2	Installing	RPMs Using YUM	4
	2.1 2.2 2.3	Repository Configuration	4
3	Installing	RPMs Manually	6
	3.1 3.2	Package List	
4	Obtaining	License	8
	4.1 4.2 4.3	License Type  Node Information  License Installation	8
5	Configuri	ng Server and Plugin	. 9
	5.1 5.2 5.3	Plugin Factory  Logger  PocketSphinx	9
6	Validating	g Setup	10
	6.1 6.2	Launching Server	

# 1 Overview

This guide describes how to obtain and install binary packages for the PocketSphinx plugin to the UniMRCP server on Red Hat-based Linux distributions. The document is intended for system administrators and developers.

#### 1.1 Applicable Versions

Instructions provided in this guide are applicable to the following versions.



UniMRCP 1.5.0 and above

UniMRCP PocketSphinx Plugin 1.0.0 and above

### 1.2 Supported Distributions

UniMRCP binary packages are currently available only for x86\_64 (64-bit) architecture.

Operating System	32-bit	64-bit
Red Hat / Cent OS 6		<b>√</b>
Red Hat / Cent OS 7		<b>✓</b>

Note: packages for other distributions can be made available upon request. For more information, contact <a href="mailto:services@unimrcp.org">services@unimrcp.org</a>.

#### 1.3 Authentication

UniMRCP binary packages are available to authenticated users only. In order to register a free account with UniMRCP, please visit the following page.



https://www.unimrcp.org/profile-registration

Note: a new account needs to be verified and activated prior further proceeding.

# 2 Installing RPMs Using YUM

Using the Yellowdog Updater, Modifier (yum), a command-line package management utility for Red Hat-based distributions, is recommended for installation of UniMRCP binary packages.

### 2.1 Repository Configuration

The content of a typical yum configuration file, to be placed in /etc/yum.repos.d/unimrcp.repo, is provided below.

```
[unimrcp]
name=UniMRCP Packages for Red Hat / Cent OS-$releasever $basearch
baseurl=https://username:password@unimrcp.org/repo/yum/main/rhel$releasever/$basearch/
enabled=1
sslverify=1
gpgcheck=1
gpgkey=https://unimrcp.org/keys/unimrcp-gpg-key.public

[unimrcp-noarch]
name=UniMRCP Packages for Red Hat / Cent OS-$releasever noarch
baseurl=https://username:password@unimrcp.org/repo/yum/main/rhel$releasever/noarch/
enabled=1
sslverify=1
gpgcheck=1
gpgcheck=1
gpgkey=https://unimrcp.org/keys/unimrcp-gpg-key.public
```

The username and password fields included in the HTTPS URI must be replaced with the corresponding account credentials.

### 2.2 Repository Verification

In order to verify that yum can properly connect and access the UniMRCP repository, the following command can be used.

```
yum repolist unimrcp-noarch
```

where *unimrcp* and *unimrcp-noarch* are names of the sections set in the yum configuration file above.

In order to retrieve a list of packages the UniMRCP repository provides, the following command can be used.

```
yum --disablerepo="*" --enablerepo="unimrcp" list available
```

yum --disablerepo="\*" --enablerepo="unimrcp-noarch" list available

# 2.3 PocketSphinx Plugin Installation

In order to install the PocketSphinx plugin package, including all the dependencies, use the following command.

#### yum install unimrcp-pocketsphinx

In order to install the en-US model package for PocketSphinx, use the following command.

#### yum install unimrcp-pocketsphinx-model-en-US

Note: this package provides acoustic data files required for the PocketSphinx engine to perform recognition for the en-US language. Packages for other languages can be made available upon request.

In order to install the additional data files for the sample client application *umc*, the following command can be used.

#### yum install umc-addons

Note: this package is optional and provides additional data which can be used for validation of basic setup.

# 3 Installing RPMs Manually

UniMRCP RPM packages can be installed manually using the *rpm* utility. Note, however, that the system administrator should take care of package dependencies and install all the packages in appropriate order.

The RPM packages have the following naming convention:

\$packagename-\$universion-\$packageversion.el\$rhelversion.\$arch.rpm

#### where

- packagename is the name of a package
- *universion* is the UniMRCP version
- packageversion is the RPM release version
- rhelversion is the Red Hat version
- arch is the architecture (x86\_64, i686, ...)

#### 3.1 Package List

The following is a list of UniMRCP RPM packages required for the installation of PocketSphinx plugin.

Package Name	Description
unimrcp-pocketsphinx	PocketSphinx plugin to the server.
unimrcp-pocketsphinx-model-en-US	PocketSphinx en-US language files.
umc-addons	Sample en-US data files used with umc. [Optional]
unilicnodegen	Node information retrieval tool, required for license deployment.
unimrcp-server	Shared library and application of the server.
unimrcp-client	Shared libraries and sample applications of the client. [Optional]
unimrcp-demo-plugins	Set of demo plugins to the server. [Optional]
unimrcp-common	Data common for the client and the server.
uniapr	UniMRCP edition of the Apache Portable Runtime (APR) library.

uniapr-util	UniMRCP edition of the Apache Portable Runtime Utility (APR-Util) library.
unisofia-sip	UniMRCP edition of the Sofia SIP library.

### 3.2 Package Installation Order

Note that all the RPM packages provided by UniMRCP are signed by a GNU Privacy Guard (GPG) key. Before starting the installation, you may need to import the public key in order to allow the *rpm* utility to verify the packages.

```
rpm --import https://unimrcp.org/keys/unimrcp-gpg-key.public
```

Packages for the APR, APR-Util and Sofia-SIP libraries must be installed first.

```
rpm -ivh uniapr-$aprversion-$packageversion.el$rhelversion.$arch.rpm rpm -ivh uniapr-util-$apuversion-$packageversion.el$rhelversion.$arch.rpm rpm -ivh unisofia-sip-$sofiaversion-$packageversion.el$rhelversion.$arch.rpm
```

Then, a package containing common data for the client and the server, and a package for the server should follow.

```
rpm -ivh unimrcp-common-$universion-$packageversion.el$rhelversion.$arch.rpm rpm -ivh unimrcp-server-$universion-$packageversion.el$rhelversion.$arch.rpm
```

Next, a package containing the utility tool *unilicnodegen*, required for license deployment.

```
rpm -ivh unilicnodegen-$toolversion-$packageversion.el$rhelversion.$arch.rpm
```

Next, a package containing the PocketSphinx plugin should follow.

```
rpm -ivh unimrcp-pocketsphinx-$universion-$packageversion.el$rhelversion.$arch.rpm
```

Finally, one or more packages corresponding to a particular language should follow.

```
rpm -ivh unimrcp-pocketsphinx-model-en-US-$universion-$packageversion.el$rhelversion.noarch.rpm
```

# 4 Obtaining License

The PocketSphinx plugin to the UniMRCP server is a commercial product, which requires a license file to be installed.

### 4.1 License Type

The following license types are available:

- Trial
- Production
- Test and Development

#### 4.2 Node Information

The license files are bound to a node the product is installed on. In order to obtain a license, the corresponding node information needs to be retrieved and submitted for generation of a license file.

Use the installed tool unilicnodegen to retrieve the node information.

#### /opt/unimrcp/bin/unilicnodegen

As a result, a text file *uninode.info* will be saved in the current directory. Submit the file *uninode.info* for license generation to services@unimrcp.org by mentioning the product name in the subject.

#### 4.3 License Installation

The license file needs to be placed into the directory /opt/unimrcp/data.

cp umspocketsphinx\_\*.lic /opt/unimrcp/data

# 5 Configuring Server and Plugin

### 5.1 Plugin Factory

In order to load the PocketSphinx plugin into the UniMRCP server, open the file *unimrcpserver.xml*, located in the directory */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following entry under the XML element */opt/unimrcp/conf*, and add the following element */opt/unimrcp/conf*, and add the following element */opt/unimrcp/conf*.

# 5.2 Logger

In order to enable log output from the plugin and set filtering rules, open the configuration file *logger.xml*, located in the directory */opt/unimrcp/conf*, and add the following entry under the element *<sources>*.

```
<source name="PS" priority="INFO" masking="NONE"/>
```

#### 5.3 PocketSphinx

The configuration file of the plugin is located in /opt/unimrcp/conf/umspocketsphinx.xml and the data files are in the directory /opt/unimrcp/data/pocketsphinx.

Refer to the *Usage Guide* for more information.

# 6 Validating Setup

Validate your setup by using the sample UniMRCP client and server applications on the same host. The default configuration and data files should be sufficient for a basic test.

### 6.1 Launching Server

Launch the UniMRCP server application.

```
cd /opt/unimrcp/bin
./unimrcpserver
```

In the server log output, check whether the plugin is normally loaded.

```
[INFO] Load Plugin [PS-Recog-1] [/opt/unimrcp/plugin/umspocketsphinx.so]
```

Next, check for the license information.

#### [NOTICE] UniMRCP PocketSphinx License

-product name: umspocketsphinx

-product version: 1.0.0 -license owner: Name -license type: trial -issue date: 2017-01-28 -exp date: 2017-02-27

-channel count: 2 -feature set: 0

#### 6.2 Launching Client

Note: the optional package *umc-addons* must be installed for this test to work.

Launch the sample UniMRCP client application *umc*.

```
cd /opt/unimrcp/bin
./umc
```

Run a typical speech recognition scenario by issuing the command *run ps1* from the console of the *umc* client application.

#### run ps1

This command sends a RECOGNIZE request to the server and then starts streaming a sample audio input file *callsteve.pcm* to recognize.

Check for the NLSML results to be returned as expected.

Visually inspect the log output for any possible warnings or errors.

Note that utterances are stored in the *var* directory, if the corresponding parameter is enabled in the configuration file *umspocketsphinx.xml* and/or requested by the client.